

Linear Programming

DPV Chapter 7, Part 1

Jim Royer

March 25, 2019

Uncredited diagrams are from DPV or homemade.

Linear Programming: Introduction, 1

Ingredients of Linear Programming

- ▶ a set of variables
- ▶ a set of linear equations/inequalities over these variables
- ▶ a linear objective function to min/max

An Example Problem: Maximizing Profits

Item	# made per day	profit per unit	max # per day
1	x_1	\$1	200
2	x_2	\$6	300

We also cannot make more than a total of 400 units per day of items 1 and 2 combined.

Q: What should x_1 and x_2 be to maximize profits?

Sample Problem, Continued

An Example Problem: Maximizing Profits

Item	# made per day	profit per unit	max # per day
1	x_1	\$1	200
2	x_2	\$6	300

We also cannot make more than a total of 400 units per day of items 1 and 2 combined.

The problem expressed as a linear program

Objective function	max: $x_1 + 6x_2$
Constraints	$x_1 \leq 200$ $x_2 \leq 300$ $x_1 + x_2 \leq 400$ $x_1, x_2 \geq 0$


Sample Problem, Continued

The problem expressed as a linear program

Objective function
max: $x_1 + 6x_2$

Constraints
 $x_1 \leq 200$
 $x_2 \leq 300$
 $x_1 + x_2 \leq 400$
 $x_1, x_2 \geq 0$

Figure 7.1 (a) The feasible region for a linear program. (b) Contour lines of the objective function: $x_1 + 6x_2 = c$ for different values of the profit c .



Linear Programming, 2

- ▶ The constraints describe a convex polygon. (Why?)

Generally ...

The optimum is achieved at a vertex of the feasible region. (Why?)

...except when there is no optimum. E.g.:

- ▶ the linear program is *infeasible*, meaning the constraints are so tight it is impossible to satisfy them all. E.g.: $x \leq 1, x \geq 2$.
- ▶ the feasible region is *unbounded*, meaning the constraints are so loose that the objective function takes on arbitrarily large values. E.g.: maximize $x_1 + x_2$ under $x_1, x_2 \geq 0$.

How to Solve Linear Programs


The Simplex Method

- ▶ **Warning: Far from the whole story!!**
- ▶ The feasible region is a polygon.
- ▶ Suppose p is a vertex of the feasible region polygon.
- ▶ p is a *local maximum* when the value of the objective function is larger at p and at any of its neighbors.
- ▶ The method *hill-climbs*.

```

p ← the origin
while p is not a local max do
  p ← the neighbor at which the
    obj. function is larger
return p
    
```

?? Why is the local max the true max?



Sample Problem, Continued

An Example Problem: Maximizing Profits

Item	# made per day	profit per unit	max # per day
1	x_1	\$1	200
2	x_2	\$6	300
3	x_3	\$13	

Other production constraints: $x_1 + x_2 + x_3 \leq 400$ and $x_2 + 3x_3 \leq 600$.

The problem expressed as a linear program

```


Objective function max:  $x_1 + 6x_2 + 13x_3$ 
Constraints
 $x_1 \leq 200$ 
 $x_2 \leq 300$ 
 $x_1 + x_2 + x_3 \leq 400$ 
 $x_2 + 3x_3 \leq 600$ 
 $x_1, x_2, x_3 \geq 0$ 
    
```

Sample Problem, Continued

The problem expressed as a linear program

```

Objective function max:  $x_1 + 6x_2 + 13x_3$ 
Constraints
 $x_1 \leq 200$ 
 $x_2 \leq 300$ 
 $x_1 + x_2 + x_3 \leq 400$ 
 $x_2 + 3x_3 \leq 600$ 
 $x_1, x_2, x_3 \geq 0$ 
    
```




$(0, 0, 0)$ → $(200, 0, 0)$ → $(200, 200, 0)$ → $(200, 0, 200)$ → $(0, 300, 100)$
 \$0 → \$200 → \$1400 → \$2800 → \$3100

Notes

- ▶ At higher dimensions, things are harder to visualize, but the math still works!
- ▶ There are lots of professional packages that quickly and accurately solve linear programming problems.
- ▶ So the key thing to know is: how to precisely express a problem as a LP-problem.

Bandwidth Allocation, 1

- ▶ We have a network as shown in the figure.
- ▶ The numbers on edges are max-bandwidth capacities.
- ▶ We need connections between users A&B, A&C, and B&C.
- ▶ Each connection requires at least two units of bandwidth, but more can be used.
- ▶ Connection A–B pays \$3 per bandwidth unit; A–C pays \$4 and B–C pays \$2.
- ▶ Each connection can be routed via the short route, long route, or a combination of the two.
- ?? How do we route connections to maximize profit?




Bandwidth Allocation, 2

- ▶ Each connection needs at least two units of bandwidth.
- ▶ Connection A–B pays \$3 per bandwidth unit; A–C pays \$4 and B–C pays \$2.

?? How do we route connections to maximize profit?

$$\begin{aligned} \max \quad & 3x_{AB} + 3x'_{AB} + 2x_{BC} + 2x'_{BC} + 4x_{AC} + 4x'_{AC} \\ & x_{AB} + x'_{AB} + x_{BC} + x'_{BC} \leq 10 \quad [\text{edge } (b, B)] \\ & x_{AB} + x'_{AB} + x_{AC} + x'_{AC} \leq 12 \quad [\text{edge } (a, A)] \\ & x_{BC} + x'_{BC} + x_{AC} + x'_{AC} \leq 8 \quad [\text{edge } (c, C)] \\ & x_{AB} + x'_{BC} + x'_{AC} \leq 6 \quad [\text{edge } (a, b)] \\ & x'_{AB} + x_{BC} + x'_{AC} \leq 13 \quad [\text{edge } (b, c)] \\ & x_{AB} + x'_{BC} + x_{AC} \leq 11 \quad [\text{edge } (a, c)] \\ & x_{AB} + x'_{AB} \geq 2 \\ & x_{BC} + x'_{BC} \geq 2 \\ & x_{AC} + x'_{AC} \geq 2 \\ & x_{AB}, x'_{AB}, x_{BC}, x'_{BC}, x_{AC}, x'_{AC} \geq 0 \end{aligned}$$



Solution via Simplex:

$$\begin{aligned} x_{AB} &= 0.0 \\ x'_{AB} &= 7.0 \\ x_{BC} &= 1.5 \\ x'_{BC} &= 1.5 \\ x_{AC} &= 0.5 \\ x'_{AC} &= 4.5 \end{aligned}$$

★ x_{UV} = the short path allocation for U–V

★ x'_{UV} = the long path allocation for U–V

Variations on Linear Programming, 1

LP in Standard Form

- ▶ the objective function is minimized
- ▶ the variables are constrained to be ≥ 0
- ▶ the other constraints are equations

LP in General

- ▶ the objective function is minimized or maximized
- ▶ the variables may take on negative values
- ▶ the other constraints are equations or inequalities

Reduction to Standard Form

$$\begin{aligned} \max : f & \iff \min : (-f) \\ x \text{ positive/negative} & \iff x^+, x^- \geq 0 \ \& \ x = x^+ - x^- \\ a_1x_1 + \dots + a_nx_n \leq b & \iff (\sum a_ix_i) + \mathbf{s} = b \ \& \ \mathbf{s} \geq 0 \end{aligned}$$

s as above is called a slack variable.

Variations on Linear Programming, 2

Reduction to Standard Form

$$\begin{aligned} \max : f &\iff \min : (-f) \\ x \text{ positive/negative} &\iff x^+, x^- \geq 0 \text{ \& } x = x^+ - x^- \\ a_1x_1 + \dots + a_nx_n \leq b &\iff (\sum a_ix_i) + s = b \text{ \& } s \geq 0 \end{aligned}$$

Example

$$\begin{aligned} \max: x_1 + 6x_2 \\ x_1 \leq 200 \\ x_2 \leq 300 \\ x_1 + x_2 \leq 400 \\ x_1, x_2 \geq 0 \end{aligned} \implies \begin{aligned} \min: -x_1 - 6x_2 \\ x_1 + s_1 = 200 \\ x_2 + s_2 = 300 \\ x_1 + x_2 + s_3 = 400 \\ x_1, x_2, s_1, s_2, s_3 \geq 0 \end{aligned}$$


Linear Programming in Matrix Form

Example

$$\begin{aligned} \max: x_1 + 6x_2 \\ x_1 \leq 200 \\ x_2 \leq 300 \\ x_1 + x_2 \leq 400 \\ x_1, x_2 \geq 0 \end{aligned} \implies \begin{aligned} \max: \vec{c}^T \cdot \vec{x} \\ A\vec{x} \leq \vec{b} \\ \vec{x} \geq 0 \end{aligned}$$

$$\text{where } \vec{c} = \begin{pmatrix} 1 \\ 6 \end{pmatrix}, \vec{x} = \begin{pmatrix} x_1 \\ x_2 \end{pmatrix}, \vec{b} = \begin{pmatrix} 200 \\ 300 \\ 400 \end{pmatrix}, A = \begin{pmatrix} 1 & 0 \\ 0 & 1 \\ 1 & 1 \end{pmatrix}$$

Network Flows



- (a) A network of oil pipelines.
The number on each edge is its maximum capacity.
No storage in nodes. s = source node. t = target node.
Goal: Send as much oil from s to t as the network allows.
- (b) A flow in the network, shipping 7 units.
Can we do better? How do we find out?

Network Flow as an LP Problem

- ▶ A variable for each edge: f_e = the flow on that edge.
 $0 \leq f_e \leq c_e$ = the capacity of edge e .
- ▶ Flow is **conserved** at each node except s and t :

$$\sum_{(w,u) \in E} f_{wu} = \sum_{(u,z) \in E} f_{uz}$$

- ▶ The **size** of the flow is the amount sent from s to t . By conservation:

$$\text{size}(f) = \sum_{(s,u) \in E} f_{su}$$

- ▶ **Goal:** Assign values to the f_{uv} 's that satisfy the constraints and maximize $\text{size}(f)$.
- ∴ This is a linear programming problem, so Simplex can solve these problems for us.

From Simplex to a Direct Network Flow Algorithm, 1

If you analyze how Simplex solves Network Flow Problems, it is roughly equivalent to:


Start with zero flow.

Repeat

Choose an appropriate path from s to t
Increase the flow along the path's edges
as much as possible

until there is no path that improves the flow

- (a) Initial network.
- (b) First path chosen.
- (c) Second path chosen.
- (d) Final flow.
- (e) Alternative first path.
- (f) Alternative second path.
The $b \rightarrow a$ edge cancels flow.



From Simplex to a Direct Network Flow Algorithm, 2

► **Appropriate paths** consists of two sorts of edges (u, v) :

1. (u, v) is in the network and not yet at full capacity.
 (u, v) can handle up to $c_{uv} - f_{uv}$ more flow.
2. (v, u) is in the network with flow along it.
 (u, v) can handle up to f_{vu} more flow — by canceling flow along (v, u) .

► $G^f = (V, E^f)$ is the *residual network* with two sorts of edges, (u, v) , with *residual capacities*:

$$\begin{cases} c_{uv} - f_{uv}, & \text{if } (u, v) \in E \text{ and } f_{uv} < c_{uv}; \\ f_{vu}, & \text{if } (v, u) \in E \text{ and } f_{vu} > 0. \end{cases}$$

G^f = the network of unused capacities.

The "Simplex Strategy"

Start with zero flow.

Repeat

Choose an **appropriate path** from s to t
Increase the flow along the path's edges as much as possible
until there is no path that improves the flow

From Simplex to a Direct Network Flow Algorithm, 2

The "Simplex Strategy"

Start with zero flow.

Repeat

Choose an appropriate path from s to t
Increase the flow along the path's edges as much as possible
until there is no path that improves the flow

$G^f = (V, E^f)$ is the *residual network* with edges (u, v) with

$$\text{residual capacities: } \begin{cases} c_{uv} - f_{uv}, & \text{if } (u, v) \in E \text{ and } f_{uv} < c_{uv}; \\ f_{vu}, & \text{if } (v, u) \in E \text{ and } f_{vu} > 0. \end{cases}$$

The "Simplex Strategy" in terms of G^f

$G^f \leftarrow G$ // Initially, capacity = unused flow

Repeat forever

Use BFS to find a path in G^f along which we can increase flow
if there is no such path **then quit**
if there is such a path **then revise** f and G^f


An Example

$G^f \leftarrow G$


// Initially, capacity = unused flow

Repeat forever


Use BFS to find a path in G^f along which we can increase flow
if there is such a path
then revise f and G^f
else quit



Initially



After Step 1



After Step 2

...

Flows and Cuts, 1


Definition

An s, t -cut is a partition of V into two sets L and R with $s \in L$ and $t \in R$.

$$\text{capacity}(L, R) = \sum \{ c_{uv} : (u, v) \in E, u \in L, v \in R \}.$$

Claim

For any flow f and any s, t -cut (L, R) :
 $\text{size}(f) \leq \text{capacity}(L, R)$.



The Max-Flow Min-Cut Theorem


The max flow in a network = $\min \{ \text{capacity}(L, R) : (L, R) \text{ is an } s, t\text{-cut} \}$.

Also, our algorithm finds the min-cut.

Flows and Cuts, 2

The Max-Flow Min-Cut Theorem

The max flow in a network = $\min \{ \text{capacity}(L, R) : (L, R) \text{ is an } s, t\text{-cut} \}$.



Proof: Let

- ▶ f = the algorithm's final flow
- ▶ L = nodes reachable (with positive capacity edges) from s in G^f . **Note:** $t \notin L$!
- ▶ $R = V - L$.

(Why?)

Claim: $\text{size}(f) = \text{capacity}(L, R)$.

Proof of Claim:

- ▶ The L to R edges must be at full capacity in G^f .
- ▶ The R to L edges must have 0 flow in f .

(Why?)

(Why?)

Therefore, the claim follows.

Thus, (L, R) must be a min-cut.

(Why?)

Therefore, the theorem follows.

Max Flow, Runtime

The "Simplex Strategy" in terms of G^f

$G^f \leftarrow G$

Repeat forever

Use BFS to find a path in G^f along which we can increase flow
if there is no such path **then quit**
if there is such a path **then** revise f and G^f

- ▶ Each iteration takes $O(|E|)$ time. (Why?)
- ▶ With some work (see Exercise 7.31) one can show that there are at most $O(|V| \cdot |E|)$ many iterations.
- ▶ Therefore, the total run time is $O(|V| \cdot |E|^2)$ time.